

phpSysInfo ist ein Webfrontend, dass verschiedene Informationen des Servers ausgibt.

Installation

Herunterladen und entpacken

```
mkdir phpSysInfo
cd phpSysInfo
wget http://sourceforge.net/projects/phpsysinfo/
unrar x phpsysinfo-<version>.rar
<file>
```

```
Besitzer ändern
<file>chown -R www-data:www-data phpsysinfo
```

und ins Apache-Verzeichnis verschieben

```
mv phpsysinfo /var/www/phpSysInfo
```

Wenn man jetzt die Seite aufruft, wird man vor einer Fehlermeldung stehen, die besagt, dass phpSysInfo nicht konfiguriert ist.

Konfiguration

Zur Konfiguration muss man zu erst die datei config.php.new im phpSysInfo-Verzeichnis in config.php umbenennen

```
mv config.php.new config.php
```

oder für die, die eine Sicherungskopie brauchen

```
cp config.php.new config.php
```

in diesem File muss man verschieden Dinge anpassen. Alle Funktionen sind aber gut dokumentiert

[config.php](#)

```
<?php
/**
 * PSI Config File
 *
 * PHP version 5
 *
 * @category   PHP
 * @package    PSI
 * @author     Michael Cramer <BigMichi1@users.sourceforge.net>
```

```
* @copyright 2009 phpSysInfo
* @license    http://opensource.org/licenses/gpl-2.0.php GNU General
Public License
* @version    SVN: $Id: config.php.new 412 2010-12-29 09:45:53Z
Jacky672 $
* @link       http://phpsysinfo.sourceforge.net
*/

// *****
//          MAIN PARAMETERS
// *****

/**
 * Turn on debugging of some functions and include errors and warnings
in xml and provide a popup for displaying errors
 * - false : no debug information are stored in xml or displayed
 * - true  : debug information stored in xml and displayed *be careful
if set this to true, may include sensitive information from your pc*
 */
define('PSI_DEBUG', false);

/**
 * Turn on/off compression for JavaScript file
 * - false : deactivate JavaScript compression (recommended with slow
processor)
 * - true  : activate JavaScript compression
 */
define('PSI_JS_COMPRESSION_ENABLE', true);

/**
 * Additional paths where to look for installed programs
 * Example : define('PSI_ADD_PATHS', '/opt/bin,/opt/sbin');
 */
define('PSI_ADD_PATHS', '/opt/bin,/opt/sbin');

/**
 * Plugins that should be included in xml and output (!!!plugin names
are case-sensitive!!!)
 * List of plugins should look like "plugin,plugin,plugin". See
/plugins directory
 * - define('PSI_PLUGINS', 'MDStatus,PS'); // list of plugins
 * - define('PSI_PLUGINS', false); //no plugins
 * included plugins:
 * - MDStatus      - show the raid status and whats currently going on
 * - PS            - show a process tree of all running processes
 * - PSStatus      - show a graphical representation if a process is
running or not
 * - Quotas        - show a table with all quotas that are active and
there current state
 * - SMART         - show S.M.A.R.T. information from drives that
```

```
support it
* - BAT           - show battery state on a laptop
* - ipmi          - show IPMI status
* - UpdateNotifier - show update notifications (only for Ubuntu
server)
*/
define('PSI_PLUGINS', 'PS,PSStatus');

// *****
//      DISPLAY PARAMETERS
// *****

/**
 * Define the default display mode
 * auto: let user browser choose the mode
 * dynamic: use javascript to refresh data
 * static: static page (use metatag to reload page)
 */
define('PSI_DEFAULT_DISPLAY_MODE', 'auto');

/**
 * Define the default language
 */
define('PSI_DEFAULT_LANG', 'de');

/**
 * Define the default template
 */
define('PSI_DEFAULT_TEMPLATE', 'nextgen');

/**
 * Show or hide language picklist
 */
define('PSI_SHOW_PICKLIST_LANG', true);

/**
 * Show or hide template picklist
 */
define('PSI_SHOW_PICKLIST_TEMPLATE', true);

/**
 * Define the interval for refreshing data in ms
 * - 0 = disabled
 * - 1000 = 1 second
 * - Default is 60 seconds
 */
define('PSI_REFRESH', 60000);

/**
 * Show a graph for current cpuload
```

```
* - true = displayed, but it's a performance hit (because we have to
wait to get a value, 1 second)
* - false = will not be displayed
*/
define('PSI_LOAD_BAR', true);

/**
 * Display the virtual host name and address
 * - Default is canonical host name and address
 * - Use define('PSI_USE_VHOST', true); to display virtual host name.
 */
define('PSI_USE_VHOST', true);

/**
 * Controls the units & format for network, memory and filesystem
 * - 1 KiB = 2^10 bytes = 1,024 bytes
 * - 1 KB = 10^3 bytes = 1,000 bytes
 * - 'PiB'    everything is in PeBiByte
 * - 'TiB'    everything is in TeBiByte
 * - 'GiB'    everything is in GiBiByte
 * - 'MiB'    everything is in MeBiByte
 * - 'KiB'    everything is in KiBiByte
 * - 'auto_binary' everything is automatic done if value is to big for,
e.g MiB then it will be in GiB
 * - 'PB'    everything is in PetaByte
 * - 'TB'    everything is in TeraByte
 * - 'GB'    everything is in GigaByte
 * - 'MB'    everything is in MegaByte
 * - 'KB'    everything is in KiloByte
 * - 'auto_decimal' everything is automatic done if value is to big
for, e.g MB then it will be in GB
 */
define('PSI_BYTE_FORMAT', 'auto_binary');

/**
 * Format in which temperature is displayed
 * - 'c'    shown in celsius
 * - 'f'    shown in fahrenheit
 * - 'c-f'  both shown first celsius and fahrenheit in braces
 * - 'f-c'  both shown first fahrenheit and celsius in braces
 */
define('PSI_TEMP_FORMAT', 'c');

// *****
//      SENSORS PARAMETERS
// *****

/**
 * Define the motherboard monitoring program (!!!names are case-
```

```

sensitive!!!)
* We support the following programs so far
* - LMSensors  http://www.lm-sensors.org/
* - Healthd    http://healthd.thehousleys.net/
* - HWSensors  http://www.openbsd.org/
* - MBMon
http://www.nt.phys.kyushu-u.ac.jp/shimizu/download/download.html
* - MBM5        http://mbm.livewiredev.com/
* - Coretemp
* - IPMI        http://openipmi.sourceforge.net/
* - K8Temp      http://hur.st/k8temp/
* Example: If you want to use lmsensors : define('PSI_SENSOR_PROGRAM',
'LMsensors');
*/
define('PSI_SENSOR_PROGRAM', false);

/**
* Define how to access the monitor program
* Available methods for the above list are in the following list
* default method 'command' should be fine for everybody
* !!! tcp connections are only made local and on the default port !!!
* - LMSensors  command, file
* - Healthd    command
* - HWSensors  command
* - MBMon      command, tcp
* - MBM5       file
* - Coretemp   command
* - IPMI       command
* - K8Temp     command
*/
define('PSI_SENSOR_ACCESS', 'command');

/**
* Hddtemp program
* If the hddtemp program is available we can read the temperature, if
hdd is smart capable
* !!ATTENTION!! hddtemp might be a security issue
* - define('PSI_HDD_TEMP', 'tcp');          // read data from hddtemp
daemon (localhost:7634)
* - define('PSI_HDD_TEMP', 'command');      // read data from hddtemp
programm (must be set suid)
*/
define('PSI_HDD_TEMP', false);

// *****
//      FILESYSTEM PARAMETERS
// *****

/**
* Show mount point

```

```
* - true = show mount point
* - false = do not show mount point
*/
define('PSI_SHOW_MOUNT_POINT', true);

/**
 * Show mount option
 * - true = show mount option
 * - false = do not show mount option
 */
define('PSI_SHOW_MOUNT_OPTION', true);

/**
 * Show inode usage
 * - true = display used inodes in percent
 * - false = hide them
 */
define('PSI_SHOW_INODES', true);

/**
 * Hide mounts
 * Example : define('PSI_HIDE_MOUNTS', '/home,/usr');
 */
define('PSI_HIDE_MOUNTS', '');

/**
 * Hide filesystem types
 * Example : define('PSI_HIDE_FS_TYPES', 'tmpfs,usbfs');
 */
define('PSI_HIDE_FS_TYPES', '');

/**
 * Hide partitions
 * Example : define('PSI_HIDE_DISKS', 'rootfs');
 */
define('PSI_HIDE_DISKS', '');

// *****
//      NETWORK PARAMETERS
// *****

/**
 * Hide network interfaces
 * Example : define('PSI_HIDE_NETWORK_INTERFACE', 'eth0,sit0');
 */
define('PSI_HIDE_NETWORK_INTERFACE', '');

// *****
```

```
//      UPS PARAMETERS
// *****

/**
 * Define the ups monitoring program (!!!names are case-sensitive!!!)
 * We support the following programs so far
 * - 1. Apcupsd  http://www.apcupsd.com/
 * - 2. Nut      http://www.networkupstools.org/
 * Example: If you want to use Apcupsd : define('PSI_UPS_PROGRAM',
'Apcupsd');
 */
define('PSI_UPS_PROGRAM', false);

/**
 * Apcupsd supports multiple UPSes
 * You can specify comma delimited list in the form <hostname>:<port>
or <ip>:<port>. The defaults are: 127.0.0.1:3551
 * See the following parameters in apcupsd.conf: NETSERVER, NISIP,
NISPORT
 */
define('PSI_UPS_APCUPSD_LIST', '127.0.0.1:3551');

?>
```

From:
<https://wiki.da-checka.de/> - PSwiki

Permanent link:
<https://wiki.da-checka.de/doku.php/wiki/programme/phpsysinfo?rev=1300710723>

Last update: **2011/03/21 13:32**

